

如何搬移 NOMICardDB 資料庫

1. 先『卸離』NOMICard DB。
2. 將原 C:\NOMICardDB\ 全搬到新目標路徑 X:\NOMICardDB\ (請自行更換目錄或是磁碟)。
3. 然後再把 NOMICard DB『附加』回來，挑選新路徑下的主 DB 檔案 (.mdf 檔案)。
4. 在把原 nomicarduser 加回到『附加』回去的 DB (要有 dbowner 的權限)，可用介面操作或是用以下 SQL SCRIPT。

```
use NOMICard
go
exec sp_changedbowner nomicarduser
go
```

5. 用 nomicarduser 去登錄，如登錄成功就 OK。(預設帳號密碼：UID: nomicarduser, PWD: Nomicard1234)。

注意：

1. 要用 SQL Administartor 或是 Windows Administrator 登錄才有足夠權限。
2. 『卸離』前要停止所有 ITP Windows Service 及其他連線程式。
3. 如發生無法卸離是因為有其他連線，可以用以下 SQL SCRIPT 去強制中斷連線。

Use NOMICard

```
go
DECLARE @DatabaseName nvarchar(50)
DECLARE @SPId int
DECLARE @SQL nvarchar(100)

--SET @DatabaseName = N'NOMICard'
SET @DatabaseName = DB_NAME()
DECLARE my_cursor CURSOR FAST_FORWARD FOR
SELECT SPId FROM MASTER..SysProcesses
WHERE DBId = DB_ID(@DatabaseName) AND SPId <> @@SPId

OPEN my_cursor

FETCH NEXT FROM my_cursor INTO @SPId
```

Date	Version	Filename	Page
	1.0		第 1 頁

```

WHILE @@FETCH_STATUS = 0
BEGIN
SET @SQL = 'KILL ' + CAST(@SPid as nvarchar(10))
print @SQL
EXEC sp_executeSQL @SQL
--KILL @SPid -- Causing Incorrect syntax near '@spid'.

```

```

FETCH NEXT FROM my_cursor INTO @SPID
END

```


```

CLOSE my_cursor
DEALLOCATE my_cursor

```


備註：

卸載方式如下：



Date	Version	Filename	Page
	1.0		第 2 頁

『附加』回去方式如下:



Date	Version	Filename	Page
	1.0		第 3 頁